



# **Monnit USB Driver Installation**

**Monnit Corporation**

**Version 4.0**

# Revision History

<b>Version</b>	<b>Date</b>	<b>Description</b>
0.1	1/1/12	created by Brandon Young
2.0	1/25/2012	Added Windows 7. Lynnette Padilla
2.1	2/6/2012	Edited contents and Windows 7 section.
3.0	2/22/2012	Updated for Driver version 3.3
4.0	9/5/2012	Updated for Driver version 4.0

**Contents**

Using Installer ..... 4

    Windows 7/Vista ..... 4

    Windows XP ..... 8

Manual Driver Installation ..... 9

    FOR WINDOWS 7: ..... 9

    FOR WINDOWS XP: ..... 12


## Using Installer

Monnit provides a driver installer that will quickly and easily install the driver onto your windows PC.


## Windows 7/Vista

The first step to installing the driver is knowing if your system has a 32 bit or 64 bit operating system. Most Windows 7 computers are 64 bit but not all, to find out what you are running follow these steps.


- 1) Click on the Start menu and open Control Panel
- 2) Choose "System and Security" Section



- 3) Choose "System"



- 4) Locate "System type" you can see that this computer is running 64 bit




Once you know what type of system you are running, download the correct driver installer from <http://driver.imonnit.com/>. Run the executable that is downloaded, You may need to confirm Open or Run.

Follow the onscreen instructions:


1) Next




2) Next




3) Next




#### 4) Install




#### 5) Next




#### 6) Install this driver anyway



## 7) Finish



## 8) Finish



## Windows XP

The first step to installing the driver is knowing if your system has a 32 bit or 64 bit operating system. Most Windows XP computers are 32 bit but not all, to find out what you are running follow these steps.


- 1) Click on **Start** and then **Control Panel**.
- 2) Click on the **Performance and Maintenance** link.  
**Note:** If you're viewing the Classic View of Control Panel, you won't see this link. Just double-click on the **System** icon and proceed to Step 4.
- 3) In the Performance and Maintenance window, click on the **System** link.
- 4) When the System Properties window opens, locate the **System** area to the right of the Windows logo.  
**Note:** You should be on the General tab in System Properties.
- 5) Under System: you'll see basic information about the version of Windows XP installed on your computer:
  - **Microsoft Windows XP Professional Version [year]** means you're running Windows XP 32-bit.
  - **Microsoft Windows XP Professional x64 Edition Version [year]** means you're running Windows XP 64-bit.

**Important:** There are no 64-bit versions of Windows XP Home or Windows XP Media Center Edition. If you have either of these editions of Windows XP then you're running a 32-bit operating system.

Once you know what type of system you are running, download the correct driver installer from <http://driver.imonnit.com/>. Run the executable that is downloaded, You may need to confirm Open or Run.

Follow the onscreen instructions.

When completed Device Manager will show "USB Sensor Radio Gateway"



## Manual Driver Installation

First run the driver installation file, In the event the executable is unable to complete the install follow these steps to install the driver manually.

### FOR WINDOWS 7:

1. Download the Manual Installation files from <http://driver.imonnit.com/4.0>




2. Unzip the folder to your desktop
3. Plug in the MONNIT Link USB to the USB port.
4. Open device manager (start menu, control panel, Hardware and Sound, under Devices and Printers click Device Manager.)




2. Right Click on "USB Wireless Sensor Gateway" and select "Update Driver Software"


3. Select "Browse my computer for driver software"



4. Browse to the folder you unzipped on your desktop and click Next



Once the install is successful you have properly installed this driver. Congratulations!




If you look back in Device manager you'll see the driver "USB Sensor Radio Gateway" selected when the device is plugged in



## FOR WINDOWS XP:


1. Open device manager (start menu, right click my computer, choose properties, choose hardware tab, click device manager button.)
2. with the usb installed find the M+ Link




3. right click M+ Link and choose Update Driver
4. Choose No Not this time, and click next



5. Choose "Install from a specific location", Click Next




6. Choose "Don't search I will choose the driver to install", click next



7. Click "Have Disk"
8. enter or browse to "C:\Program Files\Monnit", Press OK
9. Choose Monnit USB Radio Gateway and click next




10. Wait for the installation to complete



11. Click "Finish"



12. Back in Device manager you will now see “Monnit USB Radio Gateway”



Congratulations you've manually installed the Monnit USB Radio Gateway Driver!